



GstarCAD Network License Details Checking

GstarCAD 2025




Table of Contents

GstarCAD Network License Details Checking	3
1. Checking From GstarCAD License Manager (Server).....	3
1.1. Check The Users Who Activated The Network License from Your Server.....	3
1.2. Check the Users Who Borrowed the Network License from Your Server	4
1.3. Check the Users Who are using /were used the network license	5
2. Checking From GstarCAD Network License Dashboard.....	6
2.1 Installation.....	6
2.2 Settings of GstarCAD License Path	6
2.3 GstarCAD License Dashboard	7


GstarCAD Network License Details Checking

1. Checking From GstarCAD License Manager (Server)


1.1. Check The Users Who Activated The Network License from Your Server

GstarCAD network license supports a pool of licenses (nodes) on the server and users who have the authorization (server IP and license Port) can activate the corresponding version from their side in the same LAN. When a user quits GstarCAD 2025, the license will automatically be returned to license manager.

From the License Details, you can see the network license activation information. Select the correct product and click [License Details](#) from License manager.





For example: If your network license has three nodes and three users activated and using currently, there will be no available nodes left for other users to activate or borrow. If one of the three activated users quits GstarCAD 2025, the node will be returned to license manager, and there will be one license available which can be activated or borrowed.



1.2. Check the Users Who Borrowed the Network License from Your Server



GstarCAD network license allows users to borrow nodes from the server for a certain period. The license manager list shows the number of borrowed nodes and the number of available nodes left. The Borrowed Details option shows the information about the borrowed nodes.

For example, if your network license has a total of three nodes, and one user has borrowed a node from the server, then there will only be two available nodes left that can be activated or borrowed. The borrowed license can be automatically returned to the server on the expiration date, or the user can return it manually at any time during the validity period.



1.3. Check the Users Who are using /were used the network license

You can check the users who are currently using a network license, as well as user information during a certain period of time via the Statistical Details Options in Network License Manager. It can filter the users who are currently using the licenses, as well as those who used the licenses by options "In User, Today, Yesterday, last 7 days and Specified Days".



Note:


1. Some security software (such as anti-virus software) may cause GstarCAD Network License Manager run abnormally; In this case, you can either quit the security software or add GstarCAD Network License Manager to the trusted path.
2. The server computer name should be in English.
3. If the server computer has an old GstarCAD License Manager installed, please turn it off first, then install the latest version of GstarCAD Network License Manager.

2. Checking From GstarCAD Network License Dashboard

Download and Install GstarCAD Network License Dashboard. Please follow the steps below:

2.1 Installation

- 1) Please decompress the GstarCAD Network License Dashboard.zip file.
- 2) Please double click [ServiceInstall.bat](#).




Two icons will be created on desktop: [GstarCAD License Dashboard](#) and [GstarCAD License Path](#).



2.2 Settings of GstarCAD License Path


- 1) Please double click [GstarCAD License Path](#) icon to call the window.



- 2) Please select the location path of LogFilePath: default path:【C:\ProgramData\GstarCAD\LmsLog\liclog.log】
You may change the path of liclog.log in GstarCAD LMSTools, please select the correct path of the log file.
- 3) Please click [Start](#) button to start the service.


2.3 GstarCAD License Dashboard

- 1) Please double click [GstarCAD License Dashboard](#) icon to call the window.
- 2) Basic Setting
Please click [Basic Setting](#), and then please input the license numbers of different products that you have purchased. You can find the license numbers from the purchase orders, you may also find the license numbers on GstarCAD License Manager (Server).



- 3) Current Usage
Please click [Current Usage](#). In Current Usage, you can check the information of Product, License Assigned, License Owned, Users, Status, Start Time and Used Time.
You can choose to check the information in [Chart](#) and [List](#). You can update the information by clicking button [Update](#) and Chart and List both are updated; or you can select option [Auto Update](#) so that the information will be real-time update. You can also export the current usage list information as Excel.

Chart: Here you can view the usage graphically during a period of time, you can choose the duration by pressing and dragging in the chart. It could also help you decide whether you need more licenses or not.



List: Here you can see the detailed information:

User shows who are using the licenses.

Product shows what products are being used.

Start Time shows when the licenses are started.


Used Time shows how long the licenses have been used.

The screenshot shows the 'GstarCAD License Dashboard - Administrator' interface with the 'List' view selected. The table displays the following data:

User@PC	Product	Status	Start time	Used time
Administrator@SKY-20	GstarCAD PRO	Using	7/26/2022 3:40:04 PM	1 hours 25 minutes
Mr.robot@DESKTOP-N	GstarCAD PRO	Using	7/26/2022 4:25:12 PM	40 minutes
ovs@ovs-PC	GstarCAD PRO	Using	7/26/2022 4:48:57 PM	16 minutes



GstarCAD 2025



■ <https://www.gstarcad.net/>